

# Connect IQ App — Dual-Tank Anaerobic Reserve Tracker

Spec + ready-to-use build prompt for a Garmin Connect IQ data field that tracks the reserve, consumption, and depletion of the PCr (alactic) and glycolytic (lactic) systems in real time from power.

Companion to `white-paper-dual-tank-anaerobic-model.md` (the model this app implements).

---

## Part 1 — Why these platform choices (grounding for the prompt)

---

Before the prompt, the design decisions it encodes, so you can adjust them:

- **App type = custom Data Field**, not a widget or full app. A `Toybox.WatchUi.DataField` runs *inside* the native activity recording, so it gets live sensor data, records to the FIT file automatically, and its `compute(info)` is invoked **once per second** — which is exactly the model's  $\Delta t = 1\text{ s}$  integration step. No custom timer needed.
- **Power source = `Activity.Info.currentPower`** (Watts, from a paired power meter). Guard for `null` (coasting, sensor dropout) by treating it as 0 W.
- **Custom rendering** via `onUpdate(dc)` because we draw two gauges, not a single number. This means it must be a *full-screen* / custom layout data field, which limits it to one field slot but gives full drawing control.
- **Settings via `Application.Properties` + `settings.xml` / `properties.xml`** so  $CP$ ,  $W'$ , and the tank constants are entered in Garmin Connect / Connect IQ app store settings, not hard-coded.
- **FIT recording via `FitContributor`** — expose PCr%, glycolytic%, and consumption as recorded fields so they land in Garmin Connect and sync onward to intervals.icu / Strava for post-ride review.
- **State = two `Float s` ( $rP$ ,  $rG$ )** held on the field instance. Persist to `Storage` in `onTimerLap` / `onTimerStop` optionally; a fresh ride starts full.
- **Language = Monkey C**, min SDK targeting devices with power + Connect IQ 3.x+ (Edge 530/540/830/840/1030/1040, Forerunner 255/955/965, etc.).

**Memory/CPU:** the whole model is  $\sim 10$  float ops + 2 `Math.exp` per second — negligible. Keep the draw code allocation-free (no `new` inside `onUpdate`) to stay within data-field memory budgets.

---

## Part 2 — The model to implement (reduced dual-tank, from the white paper §4)

---

State:  $rP$  (PCr reserve, J),  $rG$  (glycolytic reserve, J). Params (from settings):  $CP$ ,  $W_{\text{prime}}$ ,  $fP$ ,  $pP_{\text{max}}$ ,  $\tau_P$ ,  $\tau_G$ ,  $lt1Frac$ ,  $\eta$ . Derived:  $cP = fP \cdot W_{\text{prime}}$ ,  $cG = (1 - fP) \cdot W_{\text{prime}}$ . Init  $rP = cP$ ,  $rG = cG$ . Session accumulators (J, ride totals):  $depP = 0$ ,  $depG = 0$  — total energy ever drawn from each tank.

Each second, with power  $P$  and  $dt = 1$ :

```

delta = P - CP
if delta > 0:                                     # DEPLETION (above CP)
    need  = delta * dt
    takeP = min(need, rP, pPmax*dt)              # PCr first, rate-limited
    rP    -= takeP; need -= takeP
    takeG = min(need, rG)                        # glycolytic covers remainder
    rG    -= takeG; need -= takeG
    depP += takeP; depG += takeG                 # accumulate lifetime depletion (J)
    exhausted = (need > 0)
    consP = takeP/dt; consG = takeG/dt          # live consumption (W)
else:                                             # RESTORATION (at/below CP)
    rP += eta * (cP - rP) * (1 - exp(-dt/tauP))
    if P < lt1Frac*CP:
        gate = (lt1Frac*CP - P) / (lt1Frac*CP)
        rG += gate * (cG - rG) * (1 - exp(-dt/tauG))
    consP = 0; consG = 0

clamp rP to [0,cP], rG to [0,cG]
pctP = 100*rP/cP; pctG = 100*rG/cG; pctW = 100*(rP+rG)/Wprime
kJ_P = depP/1000; kJ_G = depG/1000             # session totals depleted per system (kJ)

```

Optional (behind a setting): fatigue-slowed PCr recovery  $\tau_{Peff} = \tau_P * (1 + k * (1 - rG/cG))$ , and an aerobic-ramp so the CP boundary is a first-order  $A(t)$  toward  $\min(P, CP)$  with  $\tau_{Aer} \approx 25$ .

---

## Part 3 — THE BUILD PROMPT

---

Copy everything in this block into your coding agent (or use it yourself). It is written to produce a complete, compilable Connect IQ project.

You are building a Garmin Connect IQ **data field** in Monkey C that tracks two anaerobic energy reserves – phosphocreatine (PCr/alactic) and glycolytic (lactic) – live from cycling power. Produce a complete, buildable project (manifest, source, resources, settings).

### ## Deliverables

1. `manifest.xml` – a datafield app; permissions for Sensor/FitContributor; product list covering Edge 530/540/830/840/1030/1040 and Forerunner 255/955/965; min SDK 4.0.
2. `source/DualTankView.mc` – a class extending `Toybox.WatchUi.DataField`.
3. `source/DualTankApp.mc` – `Toybox.Application.AppBase` returning the data field.
4. `resources/settings/settings.xml` + `resources/settings/properties.xml` – user config.
5. `resources/strings/strings.xml`, `resources/layouts/` if needed.
6. `monkey.jungle` build file. Plus a short README with build/sideload steps.

## Model (implement EXACTLY this; dt = 1 second = one compute() call)

State (Float, held on the view): rP (PCr reserve, J), rG (glycolytic reserve, J), depP (total J ever drawn from PCr this session), depG (total J ever drawn from glycolytic).

Settings (with defaults): CP=250 (W), Wprime=20000 (J), fP=0.35, pPmax=300 (W), tauP=22 (s), tauG=360 (s), lt1Frac=0.80, eta=0.80.

Derived: cP=fP\*Wprime, cG=(1-fP)\*Wprime. On init and onTimerStart-from-fresh: rP=cP, rG=cG, depP=0, depG=0.

Each compute(info):

```
P = info.currentPower has value ? info.currentPower : 0
delta = P - CP
if delta > 0:
    need = delta
    takeP = min(need, rP, pPmax); rP -= takeP; need -= takeP
    takeG = min(need, rG); rG -= takeG; need -= takeG
    depP += takeP; depG += takeG      # session-total depletion accumulators (J)
    exhausted = need > 0; consP = takeP; consG = takeG
else:
    rP += eta*(cP - rP)*(1 - Math.exp(-1.0/tauP))
    if P < lt1Frac*CP:
        gate = (lt1Frac*CP - P)/(lt1Frac*CP)
        rG += gate*(cG - rG)*(1 - Math.exp(-1.0/tauG))
    consP = 0; consG = 0
clamp rP in [0,cP], rG in [0,cG]
pctP = 100*rP/cP; pctG = 100*rG/cG
```

Guard against CP<=0 and Wprime<=0 (skip update, show "SET CP/W").

## Rendering (onUpdate(dc)) – ASPECT-ADAPTIVE TWO-BAR LAYOUT

Pick layout from the field's aspect ratio (`w`, `h` from `dc.getWidth()/getHeight()`):

- **\*\*Very wide\*\*** (`w >= h\*3`): two **\*\*horizontal\*\*** bars SIDE BY SIDE (PCr left half, GLY right half),  
each filling LEFT→RIGHT.
- **\*\*Wide/short\*\*** (`h\*1.5 <= w < h\*3`, i.e. `w\*2 >= h\*3`): two **\*\*horizontal\*\*** bars STACKED (top = PCr, bottom = GLY); label left, "%" right.
- **\*\*Large portrait single field\*\*** (`w >= 200 && h >= 240`): two **\*\*vertical\*\*** tanks on the top ~60%,  
then a summary panel – `DEPLETED (kJ)` with per-system session totals (`mDepP/1000`, `mDepG/1000`)  
and a **\*\*Fatigue\*\*** level = `fatK\*(1 - rG/cG)\*100` (how much PCr recovery is currently slowed).
- **\*\*Square or tall\*\*** (otherwise, e.g. a **\*\*1x2\*\*** cell): two **\*\*vertical\*\*** bars SIDE BY SIDE, each  
filling BOTTOM→TOP; label above, "%" below.

Live consumption ("-NNW") is drawn inside the bar while that system drains. Same color rules in all layouts.

Color logic (per gauge, decided each frame):

- **\*\*Idle / recovering** (not being drained this frame): **\*\* DULL**, desaturated fill.
- **\*\*Actively depleting** (consumption > 0 this frame): **\*\* BRIGHT**, saturated fill.
- **\*\*Depleted** (reserve at/near 0, i.e. exhausted or pct <= ~3%): **\*\* RED**, and FLASH.

Base hues are fixed per system – **\*\*PCr = purple, GLY = green\*\***:

| System       | Idle (dull)             | Depleting (bright)       | Depleted            |
|--------------|-------------------------|--------------------------|---------------------|
| PCr (purple) | `0x5A3A6E` muted purple | `0xB44DFF` bright purple | `0xFF0000` flashing |
| GLY (green)  | `0x2E5A3A` muted green  | `0x37E85A` bright green  | `0xFF0000` flashing |

- "Depleting this frame" = `consP > 0` (PCr bar) / `consG > 0` (GLY bar). Track these as state set in compute().
- **\*\*Flash\*\*** = toggle the depleted bar between red and background each ~0.5 s. Since compute()/onUpdate  
run at 1 Hz, keep a boolean `flashOn` that flips every update and use it only when that bar is depleted;  
request extra redraws with `WatchUi.requestUpdate()` if you want a faster blink than 1 Hz.
- Draw an empty-track outline (thin) behind each bar so 0% is still visible; fill = the color above.
- Overlay per bar: left-aligned label ("PCr"/"GLY"), right-aligned "NN%", and the live draw  
("-180W") shown only while that bar is depleting.
- Optional thin combined-W'bal tick/number (pctW) in a corner; keep it small.

- Optional (if space): show running session totals "PCr N.n kJ / GLY N.n kJ" (depP/1000, depG/1000)
  - as small text – the same numbers written to the session FIT fields.
- Respect getObscurityFlags()/full-screen vs partial layouts; use dc.getWidth()/getHeight();
  - precompute fonts/colors in onLayout, no allocation inside onUpdate.
- Handle dark/light device themes via getBackgroundColor() (the dull hues above read on a dark background; if background is white, darken the dull fills ~15% for contrast).

### ## FIT recording (FitContributor) – REQUIRED

Create fields in initialize() via createField(...). Two kinds:

RECORD-level (written EVERY compute() = once per second, so they become 1 Hz streams in the FIT):

- "PCr\_pct" FLOAT, units "%", MSG\_TYPE\_RECORD → PCr reserve level each second
- "GLY\_pct" FLOAT, units "%", MSG\_TYPE\_RECORD → glycolytic reserve level each second
- "PCr\_cons" SINT16, units "W", MSG\_TYPE\_RECORD → live PCr draw (optional but useful)
- "GLY\_cons" SINT16, units "W", MSG\_TYPE\_RECORD → live glycolytic draw (optional)

You MUST call setData() on the two \*\_pct fields on every compute() tick (even during recovery

and when paused-but-recording is false, guard so you only write while the activity is recording),

guaranteeing a per-second reserve trace for the whole ride.

SESSION-level (single summary value finalized at ride end):

- "PCr\_depleted\_kJ" FLOAT, units "kJ", MSG\_TYPE\_SESSION → total energy drawn from PCr = depP/1000

- "GLY\_depleted\_kJ" FLOAT, units "kJ", MSG\_TYPE\_SESSION → total energy drawn from glycolytic = depG/1000

Update these each compute() with the running depP/1000 and depG/1000; the FIT SDK keeps the last

value as the session summary, so the recorded totals reflect the whole session at save time.

Optionally also add session mins: "PCr\_min\_pct", "GLY\_min\_pct".

Field IDs must be unique small integers. These record-level streams and session totals sync to

Garmin Connect and flow on to intervals.icu / Strava as custom data.

### ## Settings (settings.xml / properties.xml)

Expose CP, Wprime, fP, pPmax, tauP, tauG, ltlFrac, eta as editable properties with the defaults

above, sensible min/max, and clear titles/descriptions. Read them in onSettingsChanged() (or on

each compute if simpler) via Application.Properties.getValue, recomputing cP/cG and re-

clamping.

### ## Lifecycle

- compute(info) does the model step and returns a value (e.g. pctP) for single-field fallback.
- onTimerStart / onTimerReset: initialize reserves to full ( $rP=cP$ ,  $rG=cG$ ) AND zero the session depletion accumulators ( $depP=0$ ,  $depG=0$ ) if starting fresh.
- onTimerPause/onTimerStop: freeze depletion (no accumulation while paused) and stamp the pause time. onTimerResume (or a start from a stopped-not-reset timer): recover both tanks in closed form for the ENTIRE elapsed pause at rest —  $\text{cap} - (\text{cap} - R) \cdot (1 - a)^N$  for N pause-seconds
- so a long stop refills correctly even if the device stops calling compute() while paused.
- Be null-safe on all Activity.Info fields.
- Realism terms (implemented, tunable): aerobic ramp ( $\tau_{Aer}$ , first-order aerobic supply toward  $\min(P, CP)$ ; 0 = hard CP) and fatigue-slowed PCr recovery ( $\tau_{Peff} = \tau_P \cdot (1 + \text{fatK} \cdot (1 - rG/cG))$ ); fatK=0 disables). See the scaffold in `../connectiq/`.

### ## Quality bar


- Compiles with the Connect IQ SDK; no runtime allocation in onUpdate; documented constants;
  - a UNITS/ASSUMPTIONS comment block noting energies are in Joules,  $dt=1s$ , and that fp is a modeling choice. Include 3–4 inline test-trace comments describing expected behavior (single sprint drains PCr and recovers in ~30–60s; sustained supra-CP drains GLY which recovers over minutes only below LT1).

---

## Part 4 — UI sketch (what the prompt should produce)

---

Two stacked **horizontal** bars, filling left → right. Color = system hue, brightness = whether that tank is being drained right now.



- **Brightness encodes action:** a bar sitting still (below-zone, steady, or recovering) is the **dull** hue; the instant it starts supplying energy (that system's consumption > 0) it snaps to the **bright** hue — so at a glance you see *which* tank the surge is coming out of.
- **PCr bar (purple)** = "how much punch is left" — moves fast, flicks bright on any hard jump, refills (dull) in seconds of soft-pedaling.
- **GLY bar (green)** = "how much sustained dig is left" — moves slower, goes bright on sustained supra-CP efforts, only refills when you drop below LT1, and comes back over minutes.
- **Either bar** → **solid red + flash** when its tank empties, the "you've spent this system" warning.
- Flash / red border when either tank hits ~0 ( **exhausted** ).

## Part 5 — Test plan (hand these traces to the built app)

| Trace                                   | Expected                                                                     |
|-----------------------------------------|------------------------------------------------------------------------------|
| 5 s @ 800 W, then 60 s @ 100 W (CP=250) | PCr drops sharply, GLY barely moves; PCr ~fully back by ~45–60 s             |
| 3 min @ 300 W (supra-CP hold)           | PCr empties in the first ~20–40 s, then GLY bleeds steadily; both low at end |
| 8×(20 s @ 400 W / 40 s @ 120 W)         | PCr sawtooths (drains/refills each rep); GLY trends down across the set      |
| 20 min @ 150 W (endurance)              | both stay ~full; GLY slowly tops off since P < LT1                           |
| sum(PCr+GLY) vs reference W'bal         | matches a Froncioni–Clarke W'bal integrator within tolerance                 |

## Part 6 — Beyond the head unit (optional extensions)

- **intervals.icu / Strava:** because reserves are recorded as FIT fields, they appear as custom streams post-ride — no extra work. A companion server model could re-fit  $fP / \tau$  from each ride.
- **Live alerts:** trigger a Connect IQ tone/vibe when PCr < 20% (don't attack) or GLY < 20% (can't sustain).
- **Per-athlete calibration:** a one-time "sprint then hold" test to estimate  $pP_{max}$ ,  $fP$ , and  $\tau_p$  instead of defaults (see white paper §6).

- **Alternate targets:** the same model + prompt structure ports to Wahoo (no Connect IQ; would need their SDK) or a phone app reading BLE power.
- 

*This app implements the reduced dual-tank model in `white-paper-dual-tank-anaerobic-model.md`. Tank levels are model estimates for pacing, not measurements of muscle chemistry; calibrate and validate (white paper §6–7) before trusting absolute numbers.*